


## Chapter 4.9: Virtual-Memory Management

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations


### Background

- **Virtual memory** – separation of user logical memory from physical memory.
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - Allows for more efficient process creation
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation


## Transfer of a Paged Memory to Contiguous Disk Space




## Virtual Memory That is Larger Than Physical Memory



## Virtual-address Space



## Shared Library Using Virtual Memory



## Page Fetch Policy

- **Demand paging** transfers a page to RAM if a reference to that page has raised a page fault
  - CON: “Many” initial page faults when a task starts
  - PRO: You only transfer what you really need
- **Pre-Paging** transfers more pages from disk to RAM additionally to the demanded page
  - PRO: improves disk I/O throughput by reading chunks
  - CON: Pre-paging is highly **speculative**
    - wastes I/O bandwidth if page will never be used
    - can destroy the working set of another task in case of page stealing

## Demand Paging

- Bring a page into memory only when it is needed
  - Less I/O needed
  - Less memory needed
  - Faster response
  - More users
- Page is needed  $\Rightarrow$  reference to it
  - invalid reference  $\Rightarrow$  abort
  - not-in-memory  $\Rightarrow$  bring to memory
- **Lazy swapper** – never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a **pager**

## Valid-Invalid Bit (Present Bit)


- With each page table entry a valid–invalid bit is associated (**v** ⇒ in-memory, **i** ⇒ not-in-memory)
- Initially valid–invalid bit is set to **i** on all entries
- Example of a page table snapshot:

Frame #	valid-invalid bit
	<b>v</b>
	<b>v</b>
	<b>v</b>
	<b>v</b>
	<b>i</b>
....	
	<b>i</b>
	<b>i</b>

page table

- During address translation, if valid–invalid bit in page table entry is **i** ⇒ page fault

## Page Table When Some Pages Are Not in Main Memory




## Page Fault

- If there is a reference to a page, first reference to that page will trap to operating system:  
**page fault**
- 1. Operating system looks at another table to decide:
  - Invalid reference  $\Rightarrow$  abort
  - Just not in memory
- 2. Get empty frame
- 3. Swap page into frame
- 4. Reset tables
- 5. Set validation bit = **v**
- 6. Restart the instruction that caused the page fault


## Page Fault (Cont.)

- Problems with instruction restart instruction
  - block move



- auto increment/decrement multiple locations
- Solutions for consistent restart
  - Touch all relevant pages before operation starts
  - Keep all modified data in registers until page faults can't take place

## Steps in Handling a Page Fault



## Performance of Demand Paging

- **Page Fault Rate**  $0 \leq p \leq 1.0$ 
  - if  $p = 0$  no page faults
  - if  $p = 1$ , every reference is a fault

- **Effective Access Time (EAT)**

$$\begin{aligned} \text{EAT} = & (1 - p) \times \text{memory access} \\ & + p (\text{page fault overhead} \\ & \quad + \text{page fault service time} \\ & \quad + \text{restart overhead} \\ & ) \end{aligned}$$

## Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- $EAT = (1 - p) \times 200 + p (8 \text{ milliseconds})$   
 $= (1 - p) \times 200 + p \times 8,000,000$   
 $= 200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then  
EAT = 8.2 microseconds.  
This is a slowdown by a factor of 40!!

## Benefits of Paged Virtual Memory

- Paged virtual memory allows other benefits during process creation:
  - Copy-on-Write
  - Memory-Mapped Files (later)




## Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially *share* the same pages in memory


If either process modifies a shared page, only then is the page copied

- COW allows more efficient process creation as only modified pages are copied
- Free pages are allocated from a **pool** of zeroed-out pages

## Before Process 1 Modifies Page C




## After Process 1 Modifies Page C



## Page Replacement

- Page replacement – find the most fitting page in memory, but not really in use
- page it out
  - Algorithm (low administrative overhead)
  - Performance – want an algorithm which will result in minimum number of page faults
  - Use **modify (dirty) bit** to reduce overhead of page transfers – only modified pages are written to disk
  - Same page may be brought into memory several times
- Large virtual memory can be provided on a smaller physical memory


## Need For Page Replacement



## Basic Page Replacement

1. Find the location of the desired page on disk
2. Find a free frame:
  - If there is a free frame, use it
  - If there is no free frame, use a page replacement algorithm to select a **victim** frame
3. Bring the desired page into the (newly) free frame; update the page and frame tables
4. Restart the process

# Page Replacement



## Replacement Policy

- Not all page frames in memory can be replaced
  - Some pages are pinned to specific page frames:
    - Most of the kernel is resident, i.e. pinned
    - some DMA can only access physical addresses, i.e. their buffers must be pinned, too (I/O Interlock)
    - A real-time task might have to pin some/all of its pages (otherwise no one can guarantee its deadline)
- OS might decide that set of pages considered for next replacement should be:
  - Limited to frames of the task having initiated page fault  
⇒ local page replacement
  - Unlimited, i.e. also frames belonging to other tasks  
⇒ global page replacement

## Cleaning Policy

*When should we page-out a “dirty” page?*

### ■ Demand Cleaning

- a page is transferred to disk only when its hosting page frame has been selected for replacement by the replacement policy
- ⇒ page faulting activity must wait for 2 page transfers (out and in)

### • Pre-Cleaning

- dirty pages are transferred to disk before their page frames are needed
- ⇒ transferring large clusters can improve disk throughput, but it makes few sense to transfer pages to disk if most of them will be modified again before they will be replaced

## Cleaning Policy

### ■ Good compromise achieved with page buffering


- Recall that pages chosen for replacement are maintained either in a free (unmodified) list or in a modified list
- Pages of the modified list can be transferred to disk periodically
- ⇒ A good compromise since:
  - not all dirty pages are transferred to disk, only those that have been chosen for next replacement
  - transferring pages is done in batch (improving disk I/O)

## Page Replacement Algorithms

- Want lowest page-fault rate
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
- In all our examples, the reference string is

**1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5**

## Graph of Page Faults Versus The Number of Frames



# First-In-First-Out (FIFO) Algorithm

reference string

7 0 1 2 0 3 0 4 2 3 0 3 2 1 2 0 1 7 0 1

7	7	7	2																
	0	0	0																
		1	1																

page frames

## FIFO Anomaly

- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- 3 frames (3 pages can be in memory at a time per process)


1	1	4	5	
2	2	1	3	9 page faults
3	3	2	4	

- 4 frames

1	1	5	4	
2	2	1	5	10 page faults
3	3	2		
4	4	3		

- Belady's Anomaly: more frames  $\Rightarrow$  more page faults


## FIFO Illustrating Belady's Anomaly



## Optimal Algorithm

- Replace page that will not be used for longest period of time
- 4 frames example

1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5



- How do you know this? (Oracle?)
- Used for measuring how well your algorithm performs



## Optimal Page Replacement

reference string

7 0 1 2 0 3 0 4 2 3 0 3 2 1 2 0 1 7 0 1

7	7	7	2		2		2		2		2						7		
	0	0	0		0		4		0		0						0		
		1	1		3		3		3		1						1		

page frames

## Least Recently Used (LRU) Algorithm

- Reference string: 1, 2, 3, 4, 1, 2, **5**, 1, 2, **3**, **4**, **5**

1	1	1	1	<b>5</b>
2	2	2	2	2
3	<b>5</b>	5	<b>4</b>	4
4	4	<b>3</b>	3	3

- Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
  - When a page needs to be changed, look at the counters to determine which are to change

# LRU Page Replacement

reference string

7 0 1 2 0 3 0 4 2 3 0 3 2 1 2 0 1 7 0 1


7	7	7	2		2		4	4	4	0			1		1		1		
	0	0	0		0		0	0	3	3			3		0		0		
		1	1		3		3	2	2	2			2		2		7		

page frames

## LRU Stack

- **Stack** implementation – keep a stack of page numbers in a double link form:
  - Page referenced:
    - move it to the top
    - requires 6 pointers to be changed
  - No search for replacement

## LRU Stack



## LRU Approximation Algorithms


### ■ Reference bit

- With each page associate a bit, initially = 0
- When page is referenced bit set to 1
- Replace the one which is 0 (if one exists)
  - We do not know the order, however

### ■ Second chance

- Need reference bit
- Clock replacement
- If page to be replaced (in clock order) has reference bit = 1 then:
  - set reference bit 0
  - leave page in memory
  - replace next page (in clock order), subject to same rules

## Second-Chance (clock) Page-Replacement Algorithm



## Counting Algorithms

- Keep a counter of the number of references that have been made to each page
- **LFU Algorithm:** replaces page with smallest count
- **MFU Algorithm:** based on the argument that the page with the smallest count was probably just brought in and has yet to be used

## Allocation of Frames

- Each process needs *minimum* number of pages
- Example: IBM 370 – 6 pages to handle SS MOVE instruction:
  - instruction is 6 bytes, might span 2 pages
  - 2 pages to handle *from*
  - 2 pages to handle *to*
- Two major allocation schemes
  - fixed allocation
  - priority allocation

## Fixed Allocation

- Equal allocation – For example, if there are 100 frames and 5 processes, give each process 20 frames.
- Proportional allocation – Allocate according to the size of process

$s_i$  = size of process  $p_i$

$S = \sum s_i$

$m$  = total number of frames

$a_i$  = allocation for  $p_i = \frac{s_i}{S} \times m$

$m = 64$

$s_i = 10$

$s_2 = 127$

$a_1 = \frac{10}{137} \times 64 \approx 5$

$a_2 = \frac{127}{137} \times 64 \approx 59$

## Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- If process  $P_i$  generates a page fault,
  - select for replacement one of its frames
  - select for replacement a frame from a process with lower priority number


## Global vs. Local Allocation

- **Global replacement** – process selects a replacement frame from the set of all frames; one process can take a frame from another
- **Local replacement** – each process selects from only its own set of allocated frames

## Thrashing

- If a process does not have “enough” pages, the page-fault rate is very high. This leads to:
  - low CPU utilization
  - operating system thinks that it needs to increase the degree of multiprogramming
  - another process added to the system
- **Thrashing**  $\equiv$  a process is busy swapping pages in and out


## Thrashing (Cont.)



## Demand Paging and Thrashing

- Why does demand paging work?  
Locality model
  - Process migrates from one locality to another
  - Localities may overlap
- Why does thrashing occur?  
 $\Sigma$  size of locality > total memory size

## Locality In A Memory-Reference Pattern






## Working-Set Model

- $\Delta \equiv$  working-set window  $\equiv$  a fixed number of page references  
Example: 10,000 instruction (instruction  $\Rightarrow$  page\_ref)
- $WSS_i$  (working set of Process  $P_i$ ) =  
total number of pages referenced in the most recent  $\Delta$  (varies in time)
  - if  $\Delta$  too small will not encompass entire locality
  - if  $\Delta$  too large will encompass several localities
  - if  $\Delta = \infty \Rightarrow$  will encompass entire program
- $D = \sum WSS_i \equiv$  total demand frames
- if  $D > m \Rightarrow$  Thrashing
- Policy if  $D > m$ , then suspend one of the processes

## Working-set model




## Keeping Track of the Working Set

- Approximate with interval timer + a reference bit
- Example:  $\Delta = 10,000$ 
  - Timer interrupts after every 5000 time units
  - Keep in memory 2 bits for each page
  - Whenever a timer interrupts copy and sets the values of all reference bits to 0
  - If one of the bits in memory == 1  $\Rightarrow$  page in working set
- Not accurate, because window is moving in large steps
  - Improvement = 10 bits and interrupt every 1000 time units

## Page-Fault Frequency Scheme


- Establish “acceptable” page-fault rate
  - If actual rate too low, process should lose frames
  - If actual rate too high, process should gain frames



## Solaris

- Maintains a list of free pages to assign faulting processes
- *Lotsfree* – threshold parameter (amount of free memory) to begin paging
- *Desfree* – threshold parameter to increasing paging (desired free)
- *Minfree* – threshold parameter to being swapping
- Paging is performed by *pageout* process
- Pageout scans pages using modified clock algorithm
- *Scanrate* is the rate at which pages are scanned. This ranges from *slowscan* to *fastscan*
- Pageout is called more frequently depending upon the amount of free memory available

## Solaris 2 Page Scanner




## Allocating Kernel Memory

- Treated differently from user memory
- Often allocated from a free-memory pool
  - Kernel requests memory for structures of varying sizes
  - Some kernel memory needs to be contiguous

## Buddy System

- Allocates memory from fixed-size segment consisting of physically-contiguous pages
- Memory allocated using **power-of-2 allocator**
  - Satisfies requests in units sized as power of 2
  - Request rounded up to next highest power of 2
  - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
    - Continue until appropriate sized chunk available


## Buddy System Allocator




## Slab Allocator

- Alternate strategy
- **Slab** is one or more physically contiguous pages
- **Cache** consists of one or more slabs
- Single cache for each unique kernel data structure
  - Each cache filled with **objects** – instantiations of the data structure
- When cache created, filled with objects marked as **free**
- When structures stored, objects marked as **used**
- If slab is full of used objects, next object allocated from empty slab
  - If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction

## Slab Allocation




## Working Sets and Page Fault Rates




## Other Issues -- Memory-Mapped Files

- Memory-mapped file I/O allows file I/O to be treated as routine memory access by **mapping** a disk block to a page in memory
- A file is initially read using demand paging. A page-sized portion of the file is read from the file system into a physical page. Subsequent reads/writes to/from the file are treated as ordinary memory accesses.
- Simplifies file access by treating file I/O through memory rather than `read()` `write()` system calls
- Also allows several processes to map the same file allowing the pages in memory to be shared

## Memory Mapped Files



# Memory-Mapped Shared Memory in Windows



## Other Issues – Page Size

- Page size selection must take into consideration:
  - fragmentation
  - table size
  - I/O overhead
  - locality



## Other Issues – TLB Reach

- TLB Reach - The amount of memory accessible from the TLB
- $\text{TLB Reach} = (\text{TLB Size}) \times (\text{Page Size})$
- Ideally, the working set of each process is stored in the TLB
  - Otherwise there is a high degree of page faults
- Increase the Page Size
  - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
  - This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation

## Other Issues – Program Structure

- Program structure
  - `Int[128,128] data;`
  - Each row is stored in one page (e.g., 512 bytes page size)
  - Program 1

```
for (j = 0; j < 128; j++)  
    for (i = 0; i < 128; i++)  
        data[i,j] = 0;
```

128 x 128 = 16,384 page faults

- Program 2

```
for (i = 0; i < 128; i++)  
    for (j = 0; j < 128; j++)  
        data[i,j] = 0;
```

128 page faults